

## Where is Autoform DM installed?

Nicole Ojeda - 2024-05-08 - Comments (0) - Autoform DM FAQs



These are the default install locations for key releases of DM, which are displayed in the table below:

<b>Windows version</b>	<b>Java version</b>	<b>DM version</b>	<b>Location</b>
----------------------------	-------------------------	-------------------	-----------------

Windows 11 Windows Server 2016/Windows 10 Windows Server 2012R2/Windows 8.1 Windows Server 2012/Windows 8 Windows Server 2008/Windows Vista	32-bit and 64- bit	10.x (Cluster)	C:\Program Files\Formpipe Software\Autoform DM\Server_10.x - [Cluster name] - [Cluster role] - [Node name]
		10.x (Standalone)	C:\Program Files\Formpipe Software\Autoform DM\Server_10.x - [Node name]
		9.x (Cluster)	C:\Program Files\Formpipe Software\Autoform DM\Server_9.x - [Cluster name] - [Cluster role] - [Node name]
		9.x (Standalone)	C:\Program Files\Formpipe Software\Autoform DM\Server_9.x - [Node name]
		8.x	C:\Program Files\Formpipe Software\Autoform DM\Server_8.x.x
		7.2	C:\Program Files (x86)\Formpipe Software\Autoform DM\Server_7.2.*\
		7.1	C:\Program Files (x86)\Formpipe Software\PDM\Server_7.1.*\
		7.0	C:\Program Files (x86)\AutoFORM\PDM\Server 7.0.*\
		6.9	C:\Program Files (x86)\AutoFORM\PDM\Server\
Windows Server 2003/Windows XP	None	7.2	C:\Program Files\EFS Technology\AUTOFORM DM\Server_7.2.*\
		7.1	C:\Program Files\EFS Technology\PDM\Server_7.1.*\
		7.0	C:\Program Files\AutoFORM\PDM\Server 6.9.*\
		6.9	C:\Program Files\AutoFORM\PDM\Server\

The version number (for example '7.0.1') will be the version of DM you have installed. The paths may have been changed from their default paths during installation. You can find the location by looking at the "Path to executable" on the "Properties" of the DM Service in services.msc.

To view the DM system requirements, click [here](#).